

ARMOR PLATE FLOOR SEALER FINISH

Floor Care PROCEDURES

DAILY MAINTENANCE

NEUTRAL FLOOR CLEANER



ALWAYS WEAR GOGGLES, GLOVES AND SLIP RESISTANT SHOES WHEN USING THIS PRODUCT.

NEVER BURNISH WITH A SOILED PAD



Remove gross soils (labels, gum). Sweep and mop floor. Place "Wet Floor" signs in area.



Dilute AP Neutral Floor Cleaner with 1 part to 80 parts water. (Replace solutions daily or when mop becomes dirty.)



Apply to sealed floors with a mop or auto-scrubber. Allow floor to dry completely.



When Dry, if needed, burnish with ultra high speed machine and ETC Medium Grey Jaguar to high gloss.

DAILY MAINTENANCE Clean & Restore

GLOSS RESTORER



ALWAYS WEAR GOGGLES, GLOVES AND SLIP RESISTANT SHOES WHEN USING THIS PRODUCT.

NEVER BURNISH WITH A SOILED PAD



Remove gross soils (labels, gum). Sweep and mop floor. Place "Wet Floor" signs in area.


CLEAN & RESTORE



Dilute AP Gloss Restorer with 1 part to 80 parts water into a lined bucket.



Make what you plan to use. Using a clean mop, dip into restorer and press out excess - do not use wringer.



Apply restorer as you would a finish, keeping 6" away from the edge. Allow to dry then buff with UHS burnisher and ETC Medium Grey Jaguar pad.

SCRUB & RECOAT

Approx - Once every 12 to 24 weeks



ALWAYS WEAR GOGGLES, GLOVES AND SLIP RESISTANT SHOES WHEN USING THIS PRODUCT.

SCRUB




Dilute AP Deep Scrub Recoating Cleaner with 1 part to 12 parts water. Scrub with ETC Red Scrubber pad.



Pick up cleaning solution with scrubber or wet vac. (Replace solution when mop water becomes dirty.) Damp mop any residues with clear water. Allow floor to dry.

RECOAT



Line Bucket with fresh liner and pour in Armor Plate Floor Sealer Finish. Using clean mop outline area to be finish, then fill in using figure eight motion. Stay 6" away from edges.



Apply as many coats as required. Allow 30-45 minutes between coats. Last coat should cover edges. (To keep clean follow DAILY MAINTENANCE directions.)

STRIP & FINISH

Approx - Once every 18 to 36 months



ALWAYS WEAR GOGGLES, GLOVES AND SLIP RESISTANT SHOES WHEN USING THIS PRODUCT.


STRIP



Remove gross soils (labels, gum). Sweep and mop floor. Place "Wet Floor" signs in area.



Divide work areas into small 5'x20' areas. Dilute 1 part Superior Stripper No Rinse Liquifying Stripper with 5 parts water. Apply enough material to ensure complete wetting.



Allow to stand 5 - 10 minutes minimum. DO NOT ALLOW SOLUTION TO DRY. Re-wet as needed.



Scrub floor with auto scrubber or floor machine using proper stripping pad to break softened film. Flip pad and replace as needed.


FINISH



Pick up solution with mop, wet vac or auto scrubber. Damp mop floor with clean water to remove all residue. Allow to dry before applying base coat.



Line Bucket with fresh liner and pour in Armor Plate Floor Sealer Finish. Pour only what you plan to use. Use clean finish mop. Dip into finish and press out excess.



To apply a full even coat, outline the area to be finished. Fill in the outlined area using a figure eight motion. Stay 6" away from edges.



Allow 30 minutes to dry in between finish coats (4-5 coats). Last coat should cover edges. Allow to dry completely (4 hours) before allowing traffic.